- Sharing physical links: Multiplexing
  - Isochronous
    - Fixed size data frames
    - Hard-edged admission control
    - Circuits
  - Asynchronous
    - Variable size packets
    - Soft admission control
    - connectionless

- Must work over a huge range of parameters
  - Delays vary
    - Speed of light is constant
    - Microseconds across a room
    - Nearly 1 second over satellite
  - Link speeds
    - Kb/s (modems,radios)
    - Gb/s (optical fibers)
  - Offered load
    - Individual characters (typing)
    - Megabits/second (files/video)
  - Number of communicating computers

- Receive and Forward Delays
  - Propagation
    - Speed of light is fixed
  - Transmission
    - Packet length / data rate
  - Processing
    - Lookups, copying, error checks
  - Queuing
    - Packets arrive in bursts
    - Dependent on other traffic

#### Losses

- Network links aren't a controlled environment
  - Subject to noise (random bit errors)
    - Include error checks
  - Backhoes (power failures, broken computers, etc)
    - redundancy
- Best effort service
  - Discard packets when buffers overflow
- Retransmit for reliable communication

- Duplicates
  - Make individual messages idempotent
  - Include nonces
- Reordering
  - Causes
    - Redundant paths
    - Losses
  - Some applications care, some don't
    - Those that care trade delay for fixing order

#### Example Problem 1: Ethernet

- Ethernet, as described by the reading ("Ethernet, distributed packet switching for local computer networks"),
  - A. Delegates arbitration of conflicting transmissions to each station;
  - B. Always guarantees the delivery of packets;
  - C. Can support an unbounded number of computers;
  - D. Has limited physical range;

#### Example Problem 1: Ethernet

- Ethernet, as described by the reading ("Ethernet, distributed packet switching for local computer networks"),
  - A. Delegates arbitration of conflicting transmissions to each station;
  - Always guarantees the delivery of packets;
  - Can support an unbounded number of computers;
    - D. Has limited physical range;

#### Example Problem 2: Ethernet

- When an Ethernet station detects interference while transmitting, it:
  - A. Completes the transmission of the packet normally.
  - B. Immediately stops transmitting, and retransmits the packet later.
  - C. Records the address of the interfering station, and sends it a subsequent *interference notification* packet
  - D. Jams the Ethernet briefly
  - E. Reports a possible security violation
  - F. Sets the *possibly corrupt* bit at the very end of the packet

#### Example Problem 2: Ethernet

- When an Ethernet station detects interference while transmitting, it:
  - Completes the transmission of the packet normally.
  - Immediately stops transmitting, and retransmits the packet later.
  - Records the address of the interfering station, and sends it a subsequent *interference notification* packet
    - D. Jams the Ethernet briefly
  - Reports a possible security violation
  - Sets the *possibly corrupt* bit at the very end of the packet

### Example Problem 3: Ethernet

- An Ethernet is a network that uses:
  - A. Luminiferous ether to carry packets.
  - B. Manchester encoding to frame bits.
  - C. Exponential back-off to resolve repeated conflicts between multiple senders.
  - D. Retransmissions to avoid congestion.

### Example Problem 3: Ethernet

- An Ethernet is a network that uses:
  - Luminiferous ether to carry packets.
  - Manchester encoding to frame bits.
  - C. Exponential back-off to resolve repeated conflicts between multiple senders.
  - Retransmissions to avoid congestion.

## Example Problem 4: Congestion

- Congestion is said to occur in a receive-andforward network when:
  - A. Communication stalls because of cycles in the flow-control dependencies.
  - B. The throughput demanded of a network link exceeds its capacity.
  - C. The volume of e-mail received by each user exceeds the rate at which users can read e-mail.
  - D. The load presented to a network link persistently exceeds its capacity.
  - E. The amount of space required to store routing tables at each node becomes burdensome.

# Example Problem 4: Congestion

- Congestion is said to occur in a receive-andforward network when:
  - Communication stalls because of cycles in the flow-control dependencies.
  - The throughput demanded of a network link exceeds its capacity.
  - The volume of e-mail received by each user exceeds the rate at which users can read e-mail.
    - D. The load presented to a network link persistently exceeds its capacity.
  - The amount of space required to store routing tables at each node becomes burdensome.